

---

R """ Miscellaneous functions and values

Author : Anders Andersen

Created On : Mon Aug 24 00:09:36 1998

Last Modified By: Anders Andersen

Last Modified On: Fri Aug 20 10:37:49 1999

Status : Unknown, Use with caution!

Copyright © 1998, 1999 Lancaster University, UK and NORUT Information Technology Ltd., Norway. See COPYING for details.

This module contains miscellaneous functions and values for the Open-ORB core platform. Some of the values (see `defaultValues`) can be changed in the users `$HOME/.pythonrc.py` file.

Instances of `ErrorObject` are used to pass exceptions between capsules. The `OpenORBEException` is the super class of all exceptions introduced by the Open-ORB core. The `debug` function is used to print debug information to `stderr` if the `DEBUG` value is true.

```
"""
# Errors and exceptions
from traceback import extract_tb, print_exception

class ErrorObject:
    R """Error object

    Used in exceptions sent (replied) to another capsule.

    """
    def __init__(self, exc=None, val=None, tb=None):
        self.exc = exc
        self.val = val
        self.tb = extract_tb(tb)
        debug_exc(exc, val, tb)

class OpenORBEException(Exception):
    R """An Open ORB exception

    Alle exceptions or errors introduced in the core ORB are of this class or of a subclass of this class.

    """
    pass

# Import user defined values (in $HOME/.pythonrc.py)
import user

# The values below can be changed in the users .pythonrc.py
defaultValues = {"DEBUG": "0", "BUFSIZ": "1024",
                  "nsPort": "50198", "nmPort": "50199", "firstPort": "50200"}

# User value with 'orb_' prefix from .pythonrc.py if they exist
for (key, value) in defaultValues.items():
    try:
        exec(key + " = user.orb_" + key)
    except AttributeError:
        exec(key + "=" + value)

# Need sys to write to stderr in debug
import sys

def debug(str="", eol="\n"):
```

```
R"""\n    Print debug information\n\n    Prints debug information if the debug flag (DEBUG) is set.\n\n    """\n    if DEBUG:\n        sys.stderr.write("%s%s" % (str,eol))\n\ndef debug_exc(exc, val, tb):\n    R"""\n        Print exception information\n\n        Prints exception information if the debug flag (DEBUG) is set.\n\n        """\n        if DEBUG:\n            print_exception(exc, val, tb)\n\n#\n# LocalWords: Aug Oct UK NORUT aacodefont defaultValues pythonrc py stderr\n#\n# LocalWords: ErrorObject OpenORBException marshall unmarshall def init exc\n#\n# LocalWords: msg BUFSIZ nsPort nmPort firstPort AttributeError str cPickle
```